

OpenZGY/C++ WORK IN PROGRESS, SUBJECT TO CHANGE

Generated by Doxygen 1.8.13

Contents

- 1 Main Page** **1**

- 2 Module Index** **3**
 - 2.1 Modules 3

- 3 Namespace Index** **5**
 - 3.1 Namespace List 5

- 4 Hierarchical Index** **7**
 - 4.1 Class Hierarchy 7

- 5 Class Index** **9**
 - 5.1 Class List 9

- 6 File Index** **11**
 - 6.1 File List 11

- 7 Module Documentation** **13**
 - 7.1 List of exceptions 13
 - 7.1.1 Detailed Description 13

- 8 Namespace Documentation** **15**
 - 8.1 OpenZGY Namespace Reference 15
 - 8.1.1 Detailed Description 16
 - 8.1.2 Enumeration Type Documentation 16
 - 8.1.2.1 DecimationType 16
 - 8.1.2.2 SampleDataType 17
 - 8.1.2.3 UnitDimension 17
 - 8.2 OpenZGY::Errors Namespace Reference 17
 - 8.2.1 Detailed Description 17
 - 8.3 OpenZGY::Formatters Namespace Reference 18
 - 8.3.1 Detailed Description 18
 - 8.4 OpenZGY::Impl Namespace Reference 18
 - 8.4.1 Detailed Description 18

9	Class Documentation	19
9.1	OpenZGY::IOContext Class Reference	19
9.1.1	Detailed Description	19
9.1.2	Member Function Documentation	19
9.1.2.1	toString()	19
9.2	OpenZGY::IZgyMeta Class Reference	20
9.2.1	Detailed Description	21
9.3	OpenZGY::IZgyReader Class Reference	21
9.3.1	Detailed Description	22
9.3.2	Member Function Documentation	22
9.3.2.1	close()	22
9.3.2.2	read() [1/3]	23
9.3.2.3	read() [2/3]	23
9.3.2.4	read() [3/3]	23
9.3.2.5	readconst()	24
9.4	OpenZGY::IZgyTools Class Reference	24
9.4.1	Detailed Description	25
9.4.2	Member Function Documentation	25
9.4.2.1	transform()	25
9.4.2.2	transform1()	26
9.5	OpenZGY::IZgyUtils Class Reference	26
9.5.1	Detailed Description	27
9.5.2	Member Function Documentation	27
9.5.2.1	deletefile()	27
9.5.2.2	utils()	27
9.6	OpenZGY::IZgyWriter Class Reference	28
9.6.1	Detailed Description	29
9.6.2	Member Function Documentation	29
9.6.2.1	close()	29
9.6.2.2	finalize()	29

9.6.2.3	write() [1/3]	30
9.6.2.4	write() [2/3]	30
9.6.2.5	write() [3/3]	31
9.6.2.6	writeconst() [1/3]	31
9.6.2.7	writeconst() [2/3]	31
9.6.2.8	writeconst() [3/3]	32
9.7	OpenZGY::ProgressWithDots Class Reference	32
9.7.1	Detailed Description	32
9.7.2	Constructor & Destructor Documentation	32
9.7.2.1	ProgressWithDots()	32
9.7.3	Member Function Documentation	33
9.7.3.1	operator()()	33
9.8	OpenZGY::SampleHistogram Class Reference	33
9.8.1	Detailed Description	34
9.9	OpenZGY::SampleStatistics Class Reference	34
9.9.1	Detailed Description	35
9.10	OpenZGY::Errors::ZgyAborted Class Reference	35
9.10.1	Detailed Description	36
9.11	OpenZGY::Errors::ZgyCorruptedFile Class Reference	36
9.11.1	Detailed Description	36
9.12	OpenZGY::Errors::ZgyEndOfFile Class Reference	37
9.12.1	Detailed Description	37
9.13	OpenZGY::Errors::ZgyError Class Reference	37
9.13.1	Detailed Description	38
9.14	OpenZGY::Errors::ZgyFormatError Class Reference	38
9.14.1	Detailed Description	39
9.15	OpenZGY::Errors::ZgyInternalError Class Reference	39
9.15.1	Detailed Description	40
9.16	OpenZGY::Errors::ZgyIoError Class Reference	40
9.16.1	Detailed Description	41

9.17	OpenZGY::Impl::ZgyMeta Class Reference	41
9.17.1	Detailed Description	42
9.18	OpenZGY::Impl::ZgyMetaAndTools Class Reference	43
9.18.1	Detailed Description	44
9.18.2	Member Function Documentation	44
9.18.2.1	transform()	44
9.18.2.2	transform1()	44
9.19	OpenZGY::Errors::ZgyMissingFeature Class Reference	45
9.19.1	Detailed Description	45
9.20	OpenZGY::Impl::ZgyReader Class Reference	46
9.20.1	Detailed Description	46
9.20.2	Constructor & Destructor Documentation	46
9.20.2.1	ZgyReader()	46
9.20.3	Member Function Documentation	47
9.20.3.1	close()	47
9.20.3.2	read() [1/3]	47
9.20.3.3	read() [2/3]	47
9.20.3.4	read() [3/3]	48
9.20.3.5	readconst()	48
9.21	OpenZGY::Errors::ZgySegmentIsClosed Class Reference	48
9.21.1	Detailed Description	49
9.22	OpenZGY::Errors::ZgyUserError Class Reference	49
9.22.1	Detailed Description	50
9.23	OpenZGY::Impl::ZgyUtils Class Reference	50
9.23.1	Detailed Description	50
9.23.2	Constructor & Destructor Documentation	50
9.23.2.1	ZgyUtils()	50
9.23.3	Member Function Documentation	51
9.23.3.1	deletefile()	51
9.24	OpenZGY::Impl::ZgyWriter Class Reference	51

9.24.1	Detailed Description	52
9.24.2	Constructor & Destructor Documentation	52
9.24.2.1	ZgyWriter()	52
9.24.2.2	~ZgyWriter()	53
9.24.3	Member Function Documentation	53
9.24.3.1	close()	53
9.24.3.2	errorflag()	53
9.24.3.3	finalize()	53
9.24.3.4	set_errorflag()	54
9.24.3.5	write() [1/3]	54
9.24.3.6	write() [2/3]	54
9.24.3.7	write() [3/3]	55
9.24.3.8	writeconst() [1/3]	55
9.24.3.9	writeconst() [2/3]	55
9.24.3.10	writeconst() [3/3]	56
9.25	OpenZGY::ZgyWriterArgs Class Reference	56
9.25.1	Detailed Description	57
9.25.2	Member Function Documentation	58
9.25.2.1	bricksizes()	58
9.25.2.2	compressor()	58
9.25.2.3	corners()	58
9.25.2.4	datarange()	58
9.25.2.5	hunit()	58
9.25.2.6	ilinc()	59
9.25.2.7	ilstart()	59
9.25.2.8	iocontext()	59
9.25.2.9	lodcompressor()	59
9.25.2.10	metafrom()	60
9.25.2.11	size()	60
9.25.2.12	xlinc()	60
9.25.2.13	xlstart()	60
9.25.2.14	zfp_compressor()	61
9.25.2.15	zfp_lodcompressor()	61
9.25.2.16	zinc()	61
9.25.2.17	zstart()	61
9.25.2.18	zunit()	61

10 File Documentation	63
10.1 api.cpp File Reference	63
10.1.1 Detailed Description	64
10.2 api.h File Reference	64
10.2.1 Detailed Description	66
10.3 example.h File Reference	67
10.3.1 Detailed Description	67
10.4 exception.h File Reference	67
10.4.1 Detailed Description	68
10.5 iocontext.h File Reference	68
10.5.1 Detailed Description	68
Index	69

Chapter 1

Main Page

The OpenZGY C++ API allows read/write access to files stored in the ZGY format. The main part of the API is here:

- [IZgyReader](#) and its [IZgyMeta](#) base class.
- [IZgyWriter](#) and its [ZgyWriterArgs](#) argument package.
- [IZgyUtils](#) for anything not read or write.
- [List of exceptions](#) that you might want to catch.
- [ProgressWithDots](#) example of progress reporting.
- [example.h](#) Example application.

Chapter 2

Module Index

2.1 Modules

Here is a list of all modules:

List of exceptions 13

Chapter 3

Namespace Index

3.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

OpenZGY	The entire public API is in this namespace	15
OpenZGY::Errors	Exceptions that can be thrown by OpenZGY	17
OpenZGY::Formatters	Operator<< for readable output of enums etc	18
OpenZGY::Impl	Implementation of the abstract interfaces in OpenZGY	18

Chapter 4

Hierarchical Index

4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

std::exception	
std::runtime_error	
OpenZGY::Errors::ZgyError	37
OpenZGY::Errors::ZgyAborted	35
OpenZGY::Errors::ZgyCorruptedFile	36
OpenZGY::Errors::ZgyEndOfFile	37
OpenZGY::Errors::ZgyFormatError	38
OpenZGY::Errors::ZgyInternalError	39
OpenZGY::Errors::ZgyIoError	40
OpenZGY::Errors::ZgyMissingFeature	45
OpenZGY::Errors::ZgySegmentIsClosed	48
OpenZGY::Errors::ZgyUserError	49
OpenZGY::IOContext	19
OpenZGY::IZgyMeta	20
OpenZGY::Impl::ZgyMeta	41
OpenZGY::Impl::ZgyMetaAndTools	43
OpenZGY::Impl::ZgyReader	46
OpenZGY::Impl::ZgyWriter	51
OpenZGY::IZgyTools	24
OpenZGY::Impl::ZgyMetaAndTools	43
OpenZGY::IZgyReader	21
OpenZGY::Impl::ZgyReader	46
OpenZGY::IZgyWriter	28
OpenZGY::Impl::ZgyWriter	51
OpenZGY::IZgyUtils	26
OpenZGY::Impl::ZgyUtils	50
OpenZGY::ProgressWithDots	32
OpenZGY::SampleHistogram	33
OpenZGY::SampleStatistics	34
OpenZGY::ZgyWriterArgs	56

Chapter 5

Class Index

5.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

OpenZGY::IOContext	Base class for backend specific context	19
OpenZGY::IZgyMeta	Base class of IZgyReader and IZgyWriter	20
OpenZGY::IZgyReader	Main API for reading ZGY files	21
OpenZGY::IZgyTools	Base class of IZgyReader and IZgyWriter	24
OpenZGY::IZgyUtils	Operations other than read and write	26
OpenZGY::IZgyWriter	Main API for creating ZGY files	28
OpenZGY::ProgressWithDots	Simple progress bar	32
OpenZGY::SampleHistogram	Histogram of all sample values on the file	33
OpenZGY::SampleStatistics	Statistics of all sample values on the file	34
OpenZGY::Errors::ZgyAborted	Exception used to abort the computation	35
OpenZGY::Errors::ZgyCorruptedFile	Exception when the ZGY file became corrupted while writing to it	36
OpenZGY::Errors::ZgyEndOfFile	Exception trying to read past EOF	37
OpenZGY::Errors::ZgyError	Exception base class for all exceptions thrown by OpenZGY	37
OpenZGY::Errors::ZgyFormatError	Exception for corrupted or unsupported ZGY file	38
OpenZGY::Errors::ZgyInternalError	Exception that might be caused by a bug in OpenZGY	39
OpenZGY::Errors::ZgyIoError	Exception from the I/O layer	40
OpenZGY::Impl::ZgyMeta	High level API for reading and writing ZGY files	41
OpenZGY::Impl::ZgyMetaAndTools	Add coordinate conversion to the concrete ZgyMeta class	43

OpenZGY::Errors::ZgyMissingFeature	
Exception for missing feature	45
OpenZGY::Impl::ZgyReader	
Concrete implementation of IZgyReader	46
OpenZGY::Errors::ZgySegmentIsClosed	
Exception used internally to request a retry	48
OpenZGY::Errors::ZgyUserError	
Exception that might be caused by the calling application	49
OpenZGY::Impl::ZgyUtils	
Concrete implementation of IZgyUtils	50
OpenZGY::Impl::ZgyWriter	
Concrete implementation of IZgyWriter	51
OpenZGY::ZgyWriterArgs	
Argument package for creating a ZGY file	56

Chapter 6

File Index

6.1 File List

Here is a list of all documented files with brief descriptions:

api.cpp	Implements the pure interfaces of the API	63
api.h	IZgyReader, IZgyWriter, and other user visible classes	64
example.h	Example program using the C++ API	67
exception.h	Defines exceptions that may be raised by OpenZGY	67
iocontext.h	Backend specific context	68

Chapter 7

Module Documentation

7.1 List of exceptions

Classes

- class `OpenZGY::Errors::ZgyError`
Exception base class for all exceptions thrown by OpenZGY.
- class `OpenZGY::Errors::ZgyFormatError`
Exception for corrupted or unsupported ZGY file.
- class `OpenZGY::Errors::ZgyCorruptedFile`
Exception when the ZGY file became corrupted while writing to it.
- class `OpenZGY::Errors::ZgyUserError`
Exception that might be caused by the calling application.
- class `OpenZGY::Errors::ZgyInternalError`
Exception that might be caused by a bug in OpenZGY.
- class `OpenZGY::Errors::ZgyEndOfFile`
Exception trying to read past EOF.
- class `OpenZGY::Errors::ZgySegmentIsClosed`
Exception used internally to request a retry.
- class `OpenZGY::Errors::ZgyAborted`
Exception used to abort the computation.
- class `OpenZGY::Errors::ZgyMissingFeature`
Exception for missing feature.
- class `OpenZGY::Errors::ZgyIoError`
Exception from the I/O layer.

7.1.1 Detailed Description

Chapter 8

Namespace Documentation

8.1 OpenZGY Namespace Reference

The entire public API is in this namespace.

Namespaces

- [Errors](#)
Exceptions that can be thrown by [OpenZGY](#).
- [Formatters](#)
operator<< for readable output of enums etc.
- [Impl](#)
Implementation of the abstract interfaces in [OpenZGY](#).

Classes

- class [IOContext](#)
Base class for backend specific context.
- class [IZgyMeta](#)
Base class of [IZgyReader](#) and [IZgyWriter](#).
- class [IZgyReader](#)
Main API for reading ZGY files.
- class [IZgyTools](#)
Base class of [IZgyReader](#) and [IZgyWriter](#).
- class [IZgyUtils](#)
Operations other than read and write.
- class [IZgyWriter](#)
Main API for creating ZGY files.
- class [ProgressWithDots](#)
Simple progress bar.
- class [SampleHistogram](#)
Histogram of all sample values on the file.
- class [SampleStatistics](#)
Statistics of all sample values on the file.
- class [ZgyWriterArgs](#)
Argument package for creating a ZGY file.

Enumerations

- enum [SampleDataType](#) { **unknown** = 1000, **int8** = 1001, **int16** = 1002, **float32** = 1003 }
- enum [UnitDimension](#) { **unknown** = 2000, **time** = 2001, **length** = 2002, **arcangle** = 2003 }
- enum [DecimationType](#) {
[DecimationType::LowPass](#) = 100, [DecimationType::WeightedAverage](#), [DecimationType::Average](#), [DecimationType::Median](#),
[DecimationType::Minimum](#), [DecimationType::Maximum](#), [DecimationType::MinMax](#), [DecimationType::Decimate](#),
[DecimationType::DecimateSkipNaN](#), [DecimationType::DecimateRandom](#), [DecimationType::AllZero](#), [DecimationType::WhiteNoise](#),
[DecimationType::MostFrequent](#), [DecimationType::MostFrequentNon0](#), [DecimationType::AverageNon0](#) }

8.1.1 Detailed Description

The entire public API is in this namespace.

The main interface is [IZgyReader](#) and [IZgyWriter](#).

8.1.2 Enumeration Type Documentation

8.1.2.1 DecimationType

```
enum OpenZGY::DecimationType [strong]
```

Possible algorithms to generate LOD bricks. We might trim this list later to what is actually in use. The "classic" ZGY only uses the first two.

Maps to `LodAlgorithm` in the implementation layer.

Enumerator

<code>LowPass</code>	Lowpass Z / decimate XY.
<code>WeightedAverage</code>	Weighted averaging (depends on global stats).
<code>Average</code>	Simple averaging.
<code>Median</code>	Somewhat more expensive averaging.
<code>Minimum</code>	Minimum value.
<code>Maximum</code>	Maximum value.
<code>MinMax</code>	Checkerboard of minimum and maximum values.
<code>Decimate</code>	Simple decimation, use first sample.
<code>DecimateSkipNaN</code>	Use first sample that is not NaN.
<code>DecimateRandom</code>	Random decimation using a fixed seed.
<code>AllZero</code>	Just fill the LOD brick with zeroes.
<code>WhiteNoise</code>	Fill with white noise, hope nobody notices.
<code>MostFrequent</code>	The value that occurs most frequently.
<code>MostFrequentNon0</code>	The non-zero value that occurs most frequently.
<code>AverageNon0</code>	Average value, but treat 0 as NaN.

8.1.2.2 SampleDataType

```
enum OpenZGY::SampleDataType [strong]
```

Value type of samples as stored on file. Data may be read and written using this type or 32-bit float.

8.1.2.3 UnitDimension

```
enum OpenZGY::UnitDimension [strong]
```

Horizontal dimension may be length or arc angle, although most applications only support length. Vertical dimension may be time or length. Vertical length is of course the same as depth. Arguably there should be separate enums for horizontal and vertical dimension since the allowed values differ.

8.2 OpenZGY::Errors Namespace Reference

Exceptions that can be thrown by [OpenZGY](#).

Classes

- class [ZgyAborted](#)
Exception used to abort the computation.
- class [ZgyCorruptedFile](#)
Exception when the ZGY file became corrupted while writing to it.
- class [ZgyEndOfFile](#)
Exception trying to read past EOF.
- class [ZgyError](#)
Exception base class for all exceptions thrown by OpenZGY.
- class [ZgyFormatError](#)
Exception for corrupted or unsupported ZGY file.
- class [ZgyInternalError](#)
Exception that might be caused by a bug in OpenZGY.
- class [ZgyIoError](#)
Exception from the I/O layer.
- class [ZgyMissingFeature](#)
Exception for missing feature.
- class [ZgySegmentsIsClosed](#)
Exception used internally to request a retry.
- class [ZgyUserError](#)
Exception that might be caused by the calling application.

8.2.1 Detailed Description

Exceptions that can be thrown by [OpenZGY](#).

8.3 OpenZGY::Formatters Namespace Reference

operator<< for readable output of enums etc.

Functions

- std::ostream & [operator<<](#) (std::ostream &os, [SampleDataType](#) value)
Output the string representation of the input enum type.
- std::ostream & [operator<<](#) (std::ostream &os, [UnitDimension](#) value)
Output the string representation of the input enum type.
- std::ostream & [operator<<](#) (std::ostream &os, [DecimationType](#) value)
Output the string representation of the input enum type.
- std::string [enumToString](#) ([SampleDataType](#) value)
Return the string representation of the input enum type.
- std::string [enumToString](#) ([UnitDimension](#) value)
Return the string representation of the input enum type.
- std::string [enumToString](#) ([DecimationType](#) value)
Return the string representation of the input enum type.

8.3.1 Detailed Description

operator<< for readable output of enums etc.

8.4 OpenZGY::Impl Namespace Reference

Implementation of the abstract interfaces in [OpenZGY](#).

Classes

- class [ZgyMeta](#)
High level API for reading and writing ZGY files.
- class [ZgyMetaAndTools](#)
Add coordinate conversion to the concrete [ZgyMeta](#) class.
- class [ZgyReader](#)
Concrete implementation of [IZgyReader](#).
- class [ZgyUtils](#)
Concrete implementation of [IZgyUtils](#).
- class [ZgyWriter](#)
Concrete implementation of [IZgyWriter](#).

8.4.1 Detailed Description

Implementation of the abstract interfaces in [OpenZGY](#).

Chapter 9

Class Documentation

9.1 OpenZGY::IOContext Class Reference

Base class for backend specific context.

```
#include <iocontext.h>
```

Public Member Functions

- virtual std::string [toString](#) () const =0

9.1.1 Detailed Description

Base class for backend specific context.

9.1.2 Member Function Documentation

9.1.2.1 toString()

```
virtual std::string OpenZGY::IOContext::toString ( ) const [pure virtual]
```

Display the context in a human readable format for debugging.

The documentation for this class was generated from the following file:


- [iocontext.h](#)

9.2 OpenZGY::IZgyMeta Class Reference

Base class of [IZgyReader](#) and [IZgyWriter](#).

```
#include <api.h>
```

Inheritance diagram for OpenZGY::IZgyMeta:



Public Types

- typedef std::int8_t **int8_t**
- typedef std::int16_t **int16_t**
- typedef std::int32_t **int32_t**
- typedef std::int64_t **int64_t**
- typedef float **float32_t**
- typedef double **float64_t**
- typedef std::array< int64_t, 3 > **size3i_t**
- typedef std::array< std::array< float64_t, 2 >, 4 > **corners_t**
- typedef std::pair< std::shared_ptr< const void >, std::int64_t > **rawdata_t**
- typedef std::function< rawdata_t(const rawdata_t &, const std::array< int64_t, 3 > &)> **compressor_t**

Public Member Functions

- virtual size3i_t **size** () const =0
Size in inline, crossline, vertical directions.
- virtual [SampleDataType](#) **datatype** () const =0
Type of samples in each brick.
- virtual std::array< float32_t, 2 > **datarange** () const =0
Used for float to int scaling.
- virtual [UnitDimension](#) **zunitdim** () const =0
Vertical dimension.
- virtual [UnitDimension](#) **hunitdim** () const =0
Horizontal dimension.
- virtual std::string **zunitname** () const =0
For annotation only. Use hunitfactor, not the name, to convert to or from SI.
- virtual std::string **hunitname** () const =0
For annotation only. Use hunitfactor, not the name, to convert to or from SI.
- virtual float32_t **zunitfactor** () const =0
Multiply by this factor to convert from storage units to SI units.
- virtual float32_t **hunitfactor** () const =0
Multiply by this factor to convert from storage units to SI units.
- virtual float32_t **zstart** () const =0
First time/depth.
- virtual float32_t **zinc** () const =0
Increment in vertical direction.

- virtual `std::array< float32_t, 2 > annotstart ()` const =0
First inline, crossline.
- virtual `std::array< float32_t, 2 > annotinc ()` const =0
Increment in inline, crossline directions.
- virtual const `corners_t & corners ()` const =0
Survey corner points in world coordinates.
- virtual const `corners_t & indexcorners ()` const =0
Survey corner points in ordinal (i,j) coordinates.
- virtual const `corners_t & annotcorners ()` const =0
Survey corner points in inline, crossline coordinates.
- virtual `size3i_t bricksize ()` const =0
Size of one brick. Almost always (64,64,64), change at your own peril.
- virtual `std::vector< size3i_t > brickcount ()` const =0
Number of bricks at each resolution (LOD) level.
- virtual `int32_t nlods ()` const =0
Number of resolution (LOD) levels.
- virtual void `meta ()` const =0
Dictionary of meta data. NOT IMPLEMENTED.
- virtual `int32_t numthreads ()` const =0
Number of threads to use. NOT IMPLEMENTED.
- virtual void `set_numthreads (int32_t)=0`
Number of threads to use. NOT IMPLEMENTED.
- virtual void `dump (std::ostream &)` const =0
Output in human readable form for debugging.
- virtual `SampleStatistics statistics ()` const =0
Statistics of all sample values on the file.
- virtual `SampleHistogram histogram ()` const =0
Histogram of all sample values on the file.

9.2.1 Detailed Description

Base class of [IZgyReader](#) and [IZgyWriter](#).

The documentation for this class was generated from the following files:


- [api.h](#)
- [api.cpp](#)

9.3 OpenZGY::IZgyReader Class Reference

Main API for reading ZGY files.

```
#include <api.h>
```

Inheritance diagram for OpenZGY::IZgyReader:



Public Member Functions

- virtual void `read` (const size3i_t &start, const size3i_t &size, float *data, int lod=0) const =0
Read an arbitrary region.
- virtual void `read` (const size3i_t &start, const size3i_t &size, std::int16_t *data, int lod=0) const =0
Read an arbitrary region with no conversion.
- virtual void `read` (const size3i_t &start, const size3i_t &size, std::int8_t *data, int lod=0) const =0
Read an arbitrary region with no conversion.
- virtual std::pair< bool, double > `readconst` (const size3i_t &start, const size3i_t &size, int lod=0, bool as_↔ float=true) const =0
Get hint about all constant region.
- virtual void `close` ()=0
Close the file and release resources.

Static Public Member Functions

- static std::shared_ptr< `IZgyReader` > `open` (const std::string &filename, const `IOContext` *iocontext=nullptr)
Open a ZGY file for reading.

Additional Inherited Members

9.3.1 Detailed Description

Main API for reading ZGY files.

Obtain a concrete instance by calling the factory method `IZgyReader::open()`. You can then use the instance to read both meta data and bulk data. It is recommended to explicitly close the file when done with it.

Note: Yes, I understand that the `open()` factory method should not have been lexically scopen inside the ostensibly pure `IZgyReader` interface. But this reduces the number of classes a library user needs to relate to.

9.3.2 Member Function Documentation

9.3.2.1 `close()`

```
virtual void OpenZGY::IZgyReader::close ( ) [pure virtual]
```

Close the file and release resources.

The `ZgyReader` destructor will call `close()` if not done already, catching and swallowing any exception. Unlike `Zgy↔ Writer::close()` forgetting to close a file that was only open for read is not a major faux pas. It is still recommended to explicitly close, though.

Implemented in `OpenZGY::Impl::ZgyReader`.

9.3.2.2 read() [1/3]

```
virtual void OpenZGY::IZgyReader::read (
    const size3i_t & start,
    const size3i_t & size,
    float * data,
    int lod = 0 ) const [pure virtual]
```

Read an arbitrary region.

The data is read into a buffer provided by the caller. The method will apply conversion storage -> float if needed.

The start position refers to the specified lod level. At lod 0 start + data.size can be up to the survey size. At lod 1 the maximum is just half that, rounded up.

Implemented in [OpenZGY::Impl::ZgyReader](#).

9.3.2.3 read() [2/3]

```
virtual void OpenZGY::IZgyReader::read (
    const size3i_t & start,
    const size3i_t & size,
    std::int16_t * data,
    int lod = 0 ) const [pure virtual]
```

Read an arbitrary region with no conversion.

As the read overload with a float buffer but only works for files with SampleDataType::int16 and does not scale the samples.

Implemented in [OpenZGY::Impl::ZgyReader](#).

9.3.2.4 read() [3/3]

```
virtual void OpenZGY::IZgyReader::read (
    const size3i_t & start,
    const size3i_t & size,
    std::int8_t * data,
    int lod = 0 ) const [pure virtual]
```

Read an arbitrary region with no conversion.

As the read overload with a float buffer but only works for files with SampleDataType::int8 and does not scale the samples.

Implemented in [OpenZGY::Impl::ZgyReader](#).

9.3.2.5 readconst()

```
virtual std::pair<bool,double> OpenZGY::IZgyReader::readconst (
    const size3i_t & start,
    const size3i_t & size,
    int lod = 0,
    bool as_float = true ) const [pure virtual]
```

Get hint about all constant region.

Check to see if the specified region is known to have all samples set to the same value. Returns a pair of (is_const, const_value).

The function only makes inexpensive checks so it might return is_const=false even if the region was in fact constant. It will not make the opposite mistake. This method is only intended as a hint to improve performance.

For int8 and int16 files the caller may specify whether to scale the values or not. Even if unscaled the function returns the value as a double.

Implemented in [OpenZGY::Impl::ZgyReader](#).

The documentation for this class was generated from the following files:


- [api.h](#)
- [api.cpp](#)

9.4 OpenZGY::IZgyTools Class Reference

Base class of [IZgyReader](#) and [IZgyWriter](#).

```
#include <api.h>
```

Inheritance diagram for OpenZGY::IZgyTools:



Public Member Functions

- virtual void [transform](#) (const corners_t &from, const corners_t &to, std::vector< std::array< float64_t, 2 >> &) const =0
General coordinate conversion of an array of points. (NOT IMPLEMENTED YET)
- virtual std::array< float64_t, 2 > [transform1](#) (const corners_t &from, const corners_t &to, const std::array< float64_t, 2 > &) const =0
General coordinate conversion of a single coordinate pair.
- virtual std::array< float64_t, 2 > [annotToIndex](#) (const std::array< float64_t, 2 > &) const =0
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [annotToWorld](#) (const std::array< float64_t, 2 > &) const =0
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [indexToAnnot](#) (const std::array< float64_t, 2 > &) const =0
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [indexToWorld](#) (const std::array< float64_t, 2 > &) const =0
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [worldToAnnot](#) (const std::array< float64_t, 2 > &) const =0
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [worldToIndex](#) (const std::array< float64_t, 2 > &) const =0
Convert a single coordinate pair.

Additional Inherited Members

9.4.1 Detailed Description

Base class of [IZgyReader](#) and [IZgyWriter](#).

9.4.2 Member Function Documentation

9.4.2.1 transform()

```
virtual void OpenZGY::IZgyTools::transform (
    const corners_t & from,
    const corners_t & to,
    std::vector< std::array< float64_t, 2 >> & ) const [pure virtual]
```

General coordinate conversion of an array of points. (NOT IMPLEMENTED YET)

Parameters

<i>from</i>	control points in the current coordinate system.
<i>to</i>	control points in the desired coordinate system.

Convert coordinates in place, with the conversion defined by giving the values of 3 arbitrary control points in both the "from" and "to" coordinate system. A common choice of arbitrary points is to use three of the lattice corners.

As a convenience the "from" and "to" parameters are declared as `corners_t` so the caller can pass `corners()`, `annotcorners()`, or `indexcorners()` directly.

Implemented in `OpenZGY::Impl::ZgyMetaAndTools`.

9.4.2.2 transform1()

```
virtual std::array<float64_t,2> OpenZGY::IZgyTools::transform1 (
    const corners_t & from,
    const corners_t & to,
    const std::array< float64_t, 2 > & ) const [pure virtual]
```

General coordinate conversion of a single coordinate pair.

Parameters

<i>from</i>	control points in the current coordinate system.
<i>to</i>	control points in the desired coordinate system.

Convert coordinates in place, with the conversion defined by giving the values of 3 arbitrary control points in both the "from" and "to" coordinate system. A common choice of arbitrary points is to use three of the lattice corners. As a convenience the "from" and "to" parameters are declared as `corners_t` so the caller can pass `corners()`, `annotcorners()`, or `indexcorners()` directly.

Implemented in `OpenZGY::Impl::ZgyMetaAndTools`.

The documentation for this class was generated from the following files:


- [api.h](#)
- [api.cpp](#)

9.5 OpenZGY::IZgyUtils Class Reference

Operations other than read and write.

```
#include <api.h>
```

Inheritance diagram for `OpenZGY::IZgyUtils`:



Public Member Functions

- virtual void `deletefile` (const std::string &filename, bool missing_ok=true)=0
Delete a file. Works both for local and cloud files.

Static Public Member Functions

- static `std::shared_ptr< IZgyUtils > utils` (const `std::string &prefix`, const `IOContext *iocontext`)
Create a new concrete instance of `IZgyUtils`.

9.5.1 Detailed Description

Operations other than read and write.

Any operations that don't fit into `IZgyReader` or `IZgyWriter` go here. Such as deleting a file. Or any other operation that does not need the file to be open first.

9.5.2 Member Function Documentation

9.5.2.1 deletefile()

```
virtual void OpenZGY::IZgyUtils::deletefile (
    const std::string & filename,
    bool missing_ok = true ) [pure virtual]
```

Delete a file. Works both for local and cloud files.

Note that the instance must be of the correct (local or cloud) type.

Implemented in `OpenZGY::Impl::ZgyUtils`.

9.5.2.2 utils()

```
std::shared_ptr< IZgyUtils > OpenZGY::IZgyUtils::utils (
    const std::string & prefix,
    const IOContext * iocontext ) [static]
```

Create a new concrete instance of `IZgyUtils`.

Parameters

<i>prefix</i>	File name or file name prefix.
<i>iocontext</i>	Credentials and other configuration.

The reason you need to supply a file name or a file name prefix is that you need to provide enough information to identify the back-end that this instance will be bound to. So if you have registered a back-end named "xx", both "xx://some/bogus/file.zgy" and just "xx://" will produce an instance that works for your XX backend,

For performance reasons you should consider caching one `IZgyUtils` instance for each back end you will be using.

Instead of just creating a new one each time you want to invoke a method. Just remember that most operations need an instance created with the same prefix.

The documentation for this class was generated from the following files:


- [api.h](#)
- [api.cpp](#)

9.6 OpenZGY::IZgyWriter Class Reference

Main API for creating ZGY files.

```
#include <api.h>
```

Inheritance diagram for OpenZGY::IZgyWriter:



Public Member Functions

- virtual void [write](#) (const size3i_t &start, const size3i_t &size, const float *data) const =0
Write an arbitrary region.
- virtual void [write](#) (const size3i_t &start, const size3i_t &size, const std::int16_t *data) const =0
Write an arbitrary region with no conversion.
- virtual void [write](#) (const size3i_t &start, const size3i_t &size, const std::int8_t *data) const =0
Write an arbitrary region with no conversion.
- virtual void [writeconst](#) (const size3i_t &start, const size3i_t &size, const float *data) const =0
Write all-constant data.
- virtual void [writeconst](#) (const size3i_t &start, const size3i_t &size, const std::int16_t *data) const =0
Write an arbitrary region with no conversion.
- virtual void [writeconst](#) (const size3i_t &start, const size3i_t &size, const std::int8_t *data) const =0
Write an arbitrary region with no conversion.
- virtual void [finalize](#) (const std::vector< [DecimationType](#) > &decimation=std::vector< [DecimationType](#) >(), const std::function< bool(std::int64_t, std::int64_t)> &progress=nullptr, bool force=false)=0
Generate low resolution data, statistics, and histogram.
- virtual void [close](#) ()=0
Flush the file to disk and close it.

Static Public Member Functions

- static std::shared_ptr< [IZgyWriter](#) > [open](#) (const [ZgyWriterArgs](#) &args)
Create a ZGY file and open it for writing.

Additional Inherited Members

9.6.1 Detailed Description

Main API for creating ZGY files.

Obtain a concrete instance by calling the factory method [IZgyWriter::open\(\)](#). All meta data is specified in the call to [open\(\)](#), so meta data will appear to be read only. You can use the instance to write bulk data. The file becomes read only once the instance is closed.

It is recommended to call [finalize\(\)](#) after all bulk has been written. but if you forget this will be called from [close\(\)](#) with default arguments. It is required to explicitly [close\(\)](#) the file when done with it, Technically the destructor will call [close\(\)](#) but being a destructor it needs to swallow any exceptions.

Note: Yes, I understand that the [open\(\)](#) factory method should not have been lexically scoped inside the ostensibly pure IZgyWriter interface. But this reduces the number of classes a library user needs to relate to.

9.6.2 Member Function Documentation

9.6.2.1 close()

```
virtual void OpenZGY::IZgyWriter::close ( ) [pure virtual]
```

Flush the file to disk and close it.

If the file has been written to, the application is encouraged to call [finalize\(\)](#) before [close\(\)](#). This gives more control over the process and allows using a progress callback to track generation of low resolution data.

The function won't bother with statistics, histogram, lowres if there has been an unrecoverable error. The headers might still be written out in case somebody wants to try some forensics.

The ZgyWriter destructor will call [close\(\)](#) if not done already, but that will catch and swallow any exception. Relying on the destructor to close the file is strongly discouraged.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.2 finalize()

```
virtual void OpenZGY::IZgyWriter::finalize (
    const std::vector< DecimationType > & decimation = std::vector< DecimationType >(),
    const std::function< bool(std::int64_t, std::int64_t)> & progress = nullptr,
    bool force = false ) [pure virtual]
```

Generate low resolution data, statistics, and histogram.

This method will be called automatically from [close\(\)](#), but in that case it is not possible to request a progress callback.

If the processing raises an exception the data is still marked as clean. Called can force a retry by passing force=True.

The C++ code is very different from Python because it needs an entirely different approach to be performant.

Parameters

<i>decimation</i>	Optionally override the decimation algorithms by passing an array of DecimationType with one entry for each level of detail. If the array is too short then the last entry is used for subsequent levels.
<i>progress</i>	Function(done, total) called to report progress. If it returns False the computation is aborted. Will be called at least one, even if there is no work.
<i>force</i>	If true, generate the low resolution data even if it appears to not be needed. Use with caution. Especially if writing to the cloud, where data should only be written once.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.3 write() [1/3]

```
virtual void OpenZGY::IZgyWriter::write (
    const size3i_t & start,
    const size3i_t & size,
    const float * data ) const [pure virtual]
```

Write an arbitrary region.

This will apply conversion float -> storage if needed.

A read/modify/write will be done if the region's start and size doesn't align with bricksize. When writing to the cloud this read/modify/write may incur performance and size penalties. So do write brick aligned data if possible. The same applies to writing compressed data where r/m/w can cause a severe loss of quality.

The start position refers to the specified lod level. At lod 0 start + data.size can be up to the survey size. At lod 1 the maximum is just half that, rounded up.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.4 write() [2/3]

```
virtual void OpenZGY::IZgyWriter::write (
    const size3i_t & start,
    const size3i_t & size,
    const std::int16_t * data ) const [pure virtual]
```

Write an arbitrary region with no conversion.

As the write overload with a float buffer but only works for files with SampleDataType::int16 and does not scale the samples.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.5 write() [3/3]

```
virtual void OpenZGY::IZgyWriter::write (
    const size3i_t & start,
    const size3i_t & size,
    const std::int8_t * data ) const [pure virtual]
```

Write an arbitrary region with no conversion.

As the write overload with a float buffer but only works for files with `SampleDataType::int8` and does not scale the samples.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.6 writeconst() [1/3]

```
virtual void OpenZGY::IZgyWriter::writeconst (
    const size3i_t & start,
    const size3i_t & size,
    const float * data ) const [pure virtual]
```

Write all-constant data.

Works as the corresponding write but the entire region is set to the same value. So the provided data buffer needs just one value, or alternatively can be passed as `&scalar_value`.

Calling this method is faster than filling a buffer with constant values and calling write. But it produces the exact same result. This is because write will automatically detect whether the input buffer is all constant.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.7 writeconst() [2/3]

```
virtual void OpenZGY::IZgyWriter::writeconst (
    const size3i_t & start,
    const size3i_t & size,
    const std::int16_t * data ) const [pure virtual]
```

Write an arbitrary region with no conversion.

As the writeconst overload with a float buffer but only works for files with `SampleDataType::int16` and does not scale the samples.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

9.6.2.8 writeconst() [3/3]

```
virtual void OpenZGY::IZgyWriter::writeconst (
    const size3i_t & start,
    const size3i_t & size,
    const std::int8_t * data ) const [pure virtual]
```

Write an arbitrary region with no conversion.

As the write overload with a float buffer but only works for files with `SampleDataType::int8` and does not scale the samples.

Implemented in [OpenZGY::Impl::ZgyWriter](#).

The documentation for this class was generated from the following files:

- [api.h](#)
- [api.cpp](#)

9.7 OpenZGY::ProgressWithDots Class Reference

Simple progress bar.

```
#include <api.h>
```

Public Member Functions

- [ProgressWithDots](#) (int length=51, std::ostream &outfile=std::cerr)
Simple progress bar.
- bool [operator\(\)](#) (std::int64_t done, std::int64_t total)
Callback invoked to report progress.

9.7.1 Detailed Description

Simple progress bar.

Progress bar that writes dots (51 by default) to standard output. This can be user as-is for simple command line apps, or you can use the source code as an example on how to write your own.

The default of 51 dots will print one dot at startup and then one additional dot for each 2% work done.

9.7.2 Constructor & Destructor Documentation

9.7.2.1 ProgressWithDots()

```
OpenZGY::ProgressWithDots::ProgressWithDots (
    int length = 51,
    std::ostream & outfile = std::cerr )
```

Simple progress bar.

Parameters

<i>length</i>	Size of progress bar, default 51 dots.
<i>outfile</i>	Stream to write output, default std::cerr

Progress bar that writes dots (51 by default) to standard output. This can be user as-is for simple command line apps, or you can use the source code as an example on how to write your own.

The default of 51 dots will print one dot at startup and then one additional dot for each 2% work done.

9.7.3 Member Function Documentation

9.7.3.1 operator()

```
bool OpenZGY::ProgressWithDots::operator() (
    std::int64_t done,
    std::int64_t total )
```

Callback invoked to report progress.

Parameters

<i>done</i>	Number of work units done.
<i>total</i>	Number of work units in total.

The callback will normally get called exactly once with done==0, before processing starts but after "total" is known. And exactly once with done==total signifying that the work is finished and the function being monitored should soon return.

This particular callback will always return true, meaning that the operation is not to be aborted.

The documentation for this class was generated from the following files:

- [api.h](#)
- [api.cpp](#)

9.8 OpenZGY::SampleHistogram Class Reference

Histogram of all sample values on the file.

```
#include <api.h>
```

Public Member Functions

- [SampleHistogram](#) (std::int64_t samplecount_in, double minvalue_in, double maxvalue_in, const std::vector<std::int64_t > &bins_in)
Create a new instance with all contents filled in.

Public Attributes

- `std::int64_t` [samplecount](#)
Sum of counts of all bins.
- `double` [minvalue](#)
Center value of data in first bin.
- `double` [maxvalue](#)
Center value of data in last bin.
- `std::vector< std::int64_t >` [bins](#)
array of counts by bin

9.8.1 Detailed Description

Histogram of all sample values on the file.

The histogram is described by the fixed total number of bins, the center value of the samples in the first bin, and the center value of the samples in the last bin.

The width of each bin is given by $(\max - \min) / (\text{nbins} - 1)$. Bin 0 holds samples with values $\min_+ \pm \text{binwidth}/2$.

This means that the total range of samples that can be represented in the histogram is actually $\min - \text{binwidth}/2$ to $\max + \text{binwidth}/2$, which is slightly larger than just $\min..max$ *unless* each of the bins can only hold a single value (e.g. data converted from 8-bit storage, in 256 bins).

This definition has some subtle effects, best illustrated by a few examples.

If the source data is `ui8_t`, the logical range is $0..255$. Assume `nbins=256`. This gives `binwidth=1`, and the true range of the histogram $-0.5..+255.5$. But since the input is integral, the actual range is just $0..255$ inclusive. Try to fill the histogram with evenly distributed random data and you end up with each bin having roughly the same number of elements.

Now consider `ui16_t`, range $0..65535$ and `nbins` is still 256. This gives `binwidth=257`, not 256. The true range of the histogram is $-128.5..+65663.5$. Try to fill the histogram with evenly distributed random data and you end up with the first and the last bin having approximately half as many elements as all the others. This is not really a problem, but may seem a bit surprising.

The documentation for this class was generated from the following file:

- [api.h](#)

9.9 OpenZGY::SampleStatistics Class Reference

Statistics of all sample values on the file.

```
#include <api.h>
```

Public Member Functions

- [SampleStatistics](#) (`std::int64_t` cnt_in, `double` sum_in, `double` ssq_in, `double` min_in, `double` max_in)
Create a new instance with all contents filled in.

Public Attributes

- `std::int64_t cnt`
Number of added samples.
- `double sum`
Sum of added samples.
- `double ssq`
Sum-of-squares of added samples.
- `double min`
Minimum added sample value.
- `double max`
Maximum added sample value.

9.9.1 Detailed Description

Statistics of all sample values on the file.

The documentation for this class was generated from the following file:


- [api.h](#)

9.10 OpenZGY::Errors::ZgyAborted Class Reference

Exception used to abort the computation.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyAborted:



Public Member Functions

- `ZgyAborted` (const std::string &arg)
Exception used to abort the computation.

Additional Inherited Members

9.10.1 Detailed Description

Exception used to abort the computation.

If the user supplied a progress callback and this callback returned false then the operation in progress will and by throwing this exception. Which means that this is not an error; it is a consequence of the abort.

The documentation for this class was generated from the following file:


- [exception.h](#)

9.11 OpenZGY::Errors::ZgyCorruptedFile Class Reference

Exception when the ZGY file became corrupted while writing to it.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyCorruptedFile:



Public Member Functions

- [ZgyCorruptedFile](#) (const std::string &arg)
Exception when the ZGY file became corrupted while writing to it.

Additional Inherited Members

9.11.1 Detailed Description

Exception when the ZGY file became corrupted while writing to it.

No further writes are allowed on this file because a previous write raised an exception and we don't know the file's state. Subsequent writes will also throw this exception.

The safe approach is to assume that the error caused the file to become corrupted. It is recommended that the application closes and deletes the file.

The documentation for this class was generated from the following file:


- [exception.h](#)

9.12 OpenZGY::Errors::ZgyEndOfFile Class Reference

Exception trying to read past EOF.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyEndOfFile:



Public Member Functions

- [ZgyEndOfFile](#) (const std::string &arg)
Exception trying to read past EOF.

Additional Inherited Members

9.12.1 Detailed Description

Exception trying to read past EOF.

This is always considered an error, and is often due to a corrupted ZGY file. So this error should probably be treated as a [ZgyFormatError](#).

The documentation for this class was generated from the following file:


- [exception.h](#)

9.13 OpenZGY::Errors::ZgyError Class Reference

Exception base class for all exceptions thrown by OpenZGY.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyError:



Protected Member Functions

- [ZgyError](#) (const std::string &arg)
Exception base class for all exceptions thrown by OpenZGY.

9.13.1 Detailed Description

Exception base class for all exceptions thrown by OpenZGY.

The documentation for this class was generated from the following file:


- [exception.h](#)

9.14 OpenZGY::Errors::ZgyFormatError Class Reference

Exception for corrupted or unsupported ZGY file.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyFormatError:



Public Member Functions

- [ZgyFormatError](#) (const std::string &arg)
Exception for corrupted or unsupported ZGY file.

Additional Inherited Members

9.14.1 Detailed Description

Exception for corrupted or unsupported ZGY file.

In some cases a corrupted file might lead to a [ZgyInternalError](#) or [ZgyEndOfFile](#) being thrown instead of this one. Because it isn't always easy to figure out the root cause.

The documentation for this class was generated from the following file:


- [exception.h](#)

9.15 OpenZGY::Errors::ZgyInternalError Class Reference

Exception that might be caused by a bug in OpenZGY.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyInternalError:



Public Member Functions

- [ZgyInternalError](#) (const std::string &arg)
Exception that might be caused by a bug in OpenZGY.

Additional Inherited Members

9.15.1 Detailed Description

Exception that might be caused by a bug in OpenZGY.

Determining whether a problem is the fault of the calling application or the OpenZGY library itself can be guesswork. Application code might choose to treat [ZgyUserError](#) and [ZgyInternalError](#) the same way.

A corrupt file might also be reported as [ZgyInternalError](#) instead of the more appropriate [ZgyFormatError](#).

The documentation for this class was generated from the following file:


- [exception.h](#)

9.16 OpenZGY::Errors::ZgyIoError Class Reference

Exception from the I/O layer.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyIoError:



Public Member Functions

- [ZgyIoError](#) (const std::string &filename, int system_errno)
Exception from the I/O layer.

Additional Inherited Members

9.16.1 Detailed Description

Exception from the I/O layer.

Some error was received from a linux syscall acting on a file. For cloud access the actual exception thrown by the back end might be reported instead of wrapping it into a [ZgyIoError](#).


The documentation for this class was generated from the following file:

- [exception.h](#)

9.17 OpenZGY::Impl::ZgyMeta Class Reference

High level API for reading and writing ZGY files.

Inheritance diagram for OpenZGY::Impl::ZgyMeta:



Public Member Functions

- virtual `std::array< int64_t, 3 > size ()` const override
Size in inline, crossline, vertical directions.
- virtual `SampleDataType datatype ()` const override
Type of samples in each brick.
- virtual `std::array< float32_t, 2 > datarange ()` const override
Used for float to int scaling.
- virtual `UnitDimension zunitdim ()` const override
Vertical dimension.
- virtual `UnitDimension hunitdim ()` const override
Horizontal dimension.
- virtual `std::string zunitname ()` const override
For annotation only. Use hunitfactor, not the name, to convert to or from SI.
- virtual `std::string hunitname ()` const override
For annotation only. Use hunitfactor, not the name, to convert to or from SI.
- virtual `float32_t zunitfactor ()` const override
Multiply by this factor to convert from storage units to SI units.
- virtual `float32_t hunitfactor ()` const override

- Multiply by this factor to convert from storage units to SI units.*

 - virtual float32_t [zstart](#) () const override
First time/depth.
 - virtual float32_t [zinc](#) () const override
Increment in vertical direction.
 - virtual std::array< float32_t, 2 > [annotstart](#) () const override
First inline, crossline.
 - virtual std::array< float32_t, 2 > [annotinc](#) () const override
Increment in inline, crossline directions.
 - virtual const corners_t & [corners](#) () const
Survey corner points in world coordinates.
 - virtual const corners_t & [indexcorners](#) () const
Survey corner points in ordinal (i,j) coordinates.
 - virtual const corners_t & [annotcorners](#) () const
Survey corner points in inline, crossline coordinates.
 - virtual std::array< int64_t, 3 > [bricksize](#) () const override
Size of one brick. Almost always (64,64,64), change at your own peril.
 - virtual std::vector< std::array< int64_t, 3 > > [brickcount](#) () const override
Number of bricks at each resolution (LOD) level.
 - virtual int32_t [nlods](#) () const override
Number of resolution (LOD) levels.
 - virtual void [meta](#) () const override
Dictionary of meta data. NOT IMPLEMENTED.
 - virtual int32_t [numthreads](#) () const override
Number of threads to use. NOT IMPLEMENTED.
 - virtual void [set_numthreads](#) (int32_t) override
Number of threads to use. NOT IMPLEMENTED.
 - virtual void [dump](#) (std::ostream &os) const override
Output in human readable form for debugging.
 - virtual [SampleStatistics](#) [statistics](#) () const override
Statistics of all sample values on the file.
 - virtual [SampleHistogram](#) [histogram](#) () const override
Histogram of all sample values on the file.

Protected Attributes

- std::shared_ptr< InternalZGY::ZgyInternalMeta > [_meta](#)
Handle to the internal metadata layer which this class wraps.

Additional Inherited Members

9.17.1 Detailed Description

High level API for reading and writing ZGY files.

The base class contains properties common to both reader and writer.

The constructor should logically have had a ZgyInternalMeta parameter for accessing the implementation layer. But due to the way the code is structured the `_meta` pointer needs to be set in the constructor for the leaf types. The `_meta` pointer is guaranteed to not be empty except while constructig the instance.

Both [ZgyReader](#) and [ZgyWriter](#) need to retain a pointer to the file descriptor. Primarily in order to explicitly close it. Relying on the shared_ptr to do this when going out of scope is dangerous because of exception handling. [ZgyWriter](#) additionally needs it when flushing metadata to disk. Since there is no file descriptor in [ZgyInternalMeta](#).

Both [ZgyReader](#) and [ZgyWriter](#) need a [ZgyInternalBulk](#) pointer to do bulk I/O. That instance in turn keeps private references to the file descriptor and the metadata but is not supposed to expose them.

The FileADT and [ZgyInternalBulk](#) pointers can be declared here since both the reader and the writer needs them. Or removed from here and duplicated in [ZgyReader](#) and [ZgyWriter](#).


The documentation for this class was generated from the following file:

- [api.cpp](#)

9.18 OpenZGY::Impl::ZgyMetaAndTools Class Reference

Add coordinate conversion to the concrete [ZgyMeta](#) class.

Inheritance diagram for OpenZGY::Impl::ZgyMetaAndTools:



Public Member Functions

- virtual void [transform](#) (const corners_t &A, const corners_t &B, std::vector< std::array< float64_t, 2 >> &data) const override
General coordinate conversion of an array of points. (NOT IMPLEMENTED YET)
- virtual std::array< float64_t, 2 > [transform1](#) (const corners_t &A, const corners_t &B, const std::array< float64_t, 2 > &point) const override
General coordinate conversion of a single coordinate pair.
- virtual std::array< float64_t, 2 > [annotToIndex](#) (const std::array< float64_t, 2 > &point) const override
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [annotToWorld](#) (const std::array< float64_t, 2 > &point) const override
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [indexToAnnot](#) (const std::array< float64_t, 2 > &point) const override
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [indexToWorld](#) (const std::array< float64_t, 2 > &point) const override
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [worldToAnnot](#) (const std::array< float64_t, 2 > &point) const override
Convert a single coordinate pair.
- virtual std::array< float64_t, 2 > [worldToIndex](#) (const std::array< float64_t, 2 > &point) const override
Convert a single coordinate pair.

Additional Inherited Members

9.18.1 Detailed Description

Add coordinate conversion to the concrete [ZgyMeta](#) class.

9.18.2 Member Function Documentation

9.18.2.1 transform()

```
virtual void OpenZGY::Impl::ZgyMetaAndTools::transform (
    const corners_t & from,
    const corners_t & to,
    std::vector< std::array< float64_t, 2 >> & ) const [override], [virtual]
```

General coordinate conversion of an array of points. (NOT IMPLEMENTED YET)

Parameters

<i>from</i>	control points in the current coordinate system.
<i>to</i>	control points in the desired coordinate system.

Convert coordinates in place, with the conversion defined by giving the values of 3 arbitrary control points in both the "from" and "to" coordinate system. A common choice of arbitrary points is to use three of the lattice corners. As a convenience the "from" and "to" parameters are declared as `corners_t` so the caller can pass [corners\(\)](#), [annotcorners\(\)](#), or [indexcorners\(\)](#) directly.

Implements [OpenZGY::IZgyTools](#).

9.18.2.2 transform1()

```
virtual std::array<float64_t,2> OpenZGY::Impl::ZgyMetaAndTools::transform1 (
    const corners_t & from,
    const corners_t & to,
    const std::array< float64_t, 2 > & ) const [override], [virtual]
```

General coordinate conversion of a single coordinate pair.

Parameters

<i>from</i>	control points in the current coordinate system.
<i>to</i>	control points in the desired coordinate system.

Convert coordinates in place, with the conversion defined by giving the values of 3 arbitrary control points in both

the "from" and "to" coordinate system. A common choice of arbitrary points is to use three of the lattice corners. As a convenience the "from" and "to" parameters are declared as `corners_t` so the caller can pass `corners()`, `annotcorners()`, or `indexcorners()` directly.

Implements [OpenZGY::IZgyTools](#).

The documentation for this class was generated from the following file:


- [api.cpp](#)

9.19 OpenZGY::Errors::ZgyMissingFeature Class Reference

Exception for missing feature.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyMissingFeature:



Public Member Functions

- [ZgyMissingFeature](#) (const std::string &arg)
Exception for missing feature.

Additional Inherited Members

9.19.1 Detailed Description

Exception for missing feature.

Raised if some optional plug-in (e.g. some cloud back end or a compressor) was loaded or explicitly requested, so we know about it, but the plug-in is not operational for some reason.


The documentation for this class was generated from the following file:

- [exception.h](#)

9.20 OpenZGY::Impl::ZgyReader Class Reference

Concrete implementation of [IZgyReader](#).

Inheritance diagram for OpenZGY::Impl::ZgyReader:



Public Member Functions

- [ZgyReader](#) (const std::string &filename, const [IOContext](#) *iocontext, bool update)
Open a ZGY file for reading.
- virtual void [read](#) (const size3i_t &start, const size3i_t &size, float *data, int lod) const override
Read an arbitrary region.
- virtual void [read](#) (const size3i_t &start, const size3i_t &size, std::int16_t *data, int lod) const override
Read an arbitrary region with no conversion.
- virtual void [read](#) (const size3i_t &start, const size3i_t &size, std::int8_t *data, int lod) const override
Read an arbitrary region with no conversion.
- virtual std::pair< bool, double > [readconst](#) (const size3i_t &start, const size3i_t &size, int lod, bool as_float) const override
Get hint about all constant region.
- void [close](#) ()
Close the file and release resources.

Additional Inherited Members

9.20.1 Detailed Description

Concrete implementation of [IZgyReader](#).

9.20.2 Constructor & Destructor Documentation

9.20.2.1 ZgyReader()

```

OpenZGY::Impl::ZgyReader::ZgyReader (
    const std::string & filename,
    const IOContext * iocontext,
    bool update )
  
```

Open a ZGY file for reading.

9.20.3 Member Function Documentation

9.20.3.1 close()

```
void OpenZGY::Impl::ZgyReader::close ( ) [virtual]
```

Close the file and release resources.

The ZgyReader destructor will call close() if not done already, catching and swallowing any exception. Unlike [ZgyWriter::close\(\)](#) forgetting to close a file that was only open for read is not a major faux pas. It is still recommended to explicitly close, though.

Implements [OpenZGY::IZgyReader](#).

9.20.3.2 read() [1/3]

```
virtual void OpenZGY::Impl::ZgyReader::read (
    const size3i_t & start,
    const size3i_t & size,
    float * data,
    int lod ) const [override], [virtual]
```

Read an arbitrary region.

The data is read into a buffer provided by the caller. The method will apply conversion storage -> float if needed.

The start position refers to the specified lod level. At lod 0 start + data.size can be up to the survey size. At lod 1 the maximum is just half that, rounded up.

Implements [OpenZGY::IZgyReader](#).

9.20.3.3 read() [2/3]

```
virtual void OpenZGY::Impl::ZgyReader::read (
    const size3i_t & start,
    const size3i_t & size,
    std::int16_t * data,
    int lod ) const [override], [virtual]
```

Read an arbitrary region with no conversion.

As the read overload with a float buffer but only works for files with SampleDataType::int16 and does not scale the samples.

Implements [OpenZGY::IZgyReader](#).

9.20.3.4 read() [3/3]

```
virtual void OpenZGY::Impl::ZgyReader::read (
    const size3i_t & start,
    const size3i_t & size,
    std::int8_t * data,
    int lod ) const [override], [virtual]
```

Read an arbitrary region with no conversion.

As the read overload with a float buffer but only works for files with `SampleDataType::int8` and does not scale the samples.

Implements [OpenZGY::IZgyReader](#).

9.20.3.5 readconst()

```
virtual std::pair<bool,double> OpenZGY::Impl::ZgyReader::readconst (
    const size3i_t & start,
    const size3i_t & size,
    int lod,
    bool as_float ) const [override], [virtual]
```

Get hint about all constant region.

Check to see if the specified region is known to have all samples set to the same value. Returns a pair of (`is_const`, `const_value`).

The function only makes inexpensive checks so it might return `is_const=false` even if the region was in fact constant. It will not make the opposite mistake. This method is only intended as a hint to improve performance.

For `int8` and `int16` files the caller may specify whether to scale the values or not. Even if unscaled the function returns the value as a double.

Implements [OpenZGY::IZgyReader](#).

The documentation for this class was generated from the following file:


- [api.cpp](#)

9.21 OpenZGY::Errors::ZgySegmentIsClosed Class Reference

Exception used internally to request a retry.

```
#include <exception.h>
```

Inheritance diagram for `OpenZGY::Errors::ZgySegmentIsClosed`:



Public Member Functions

- [ZgySegmentsClosed](#) (const std::string &arg)
Exception used internally to request a retry.

Additional Inherited Members

9.21.1 Detailed Description

Exception used internally to request a retry.

A write to the cloud failed because the region that was attempted written had already been flushed. And the cloud back-end does not allow writing it again. The calling code, still inside the [OpenZGY](#) library, should be able to catch and recover from this problem.

The documentation for this class was generated from the following file:


- [exception.h](#)

9.22 OpenZGY::Errors::ZgyUserError Class Reference

Exception that might be caused by the calling application.

```
#include <exception.h>
```

Inheritance diagram for OpenZGY::Errors::ZgyUserError:



Public Member Functions

- [ZgyUserError](#) (const std::string &arg)
Exception that might be caused by the calling application.

Additional Inherited Members

9.22.1 Detailed Description

Exception that might be caused by the calling application.

Determining whether a problem is the fault of the calling application or the OpenZGY library itself can be guesswork. Application code might choose to treat [ZgyUserError](#) and [ZgyInternalError](#) the same way.


The documentation for this class was generated from the following file:

- [exception.h](#)

9.23 OpenZGY::Impl::ZgyUtils Class Reference

Concrete implementation of [IZgyUtils](#).

Inheritance diagram for OpenZGY::Impl::ZgyUtils:



Public Member Functions

- [ZgyUtils](#) (const std::string &prefix, const [IOContext](#) *iocontext)
Create a new concrete instance of [IZgyUtils](#).
- void [deletefile](#) (const std::string &filename, bool missing_ok)
Delete a file. Works both for local and cloud files.

Additional Inherited Members

9.23.1 Detailed Description

Concrete implementation of [IZgyUtils](#).

9.23.2 Constructor & Destructor Documentation

9.23.2.1 ZgyUtils()

```

OpenZGY::Impl::ZgyUtils::ZgyUtils (
    const std::string & prefix,
    const IOContext * iocontext )
  
```

Create a new concrete instance of [IZgyUtils](#).

Parameters

<i>prefix</i>	File name or file name prefix.
<i>iocontext</i>	Credentials and other configuration.

The reason you need to supply a file name or a file name prefix is that you need to provide enough information to identify the back-end that this instance will be bound to. So if you have registered a back-end named "xx", both "xx://some/bogus/file.zgy" and just "xx://" will produce an instance that works for your XX backend,

For performance reasons you should consider caching one [IZgyUtils](#) instance for each back end you will be using. Instead of just creating a new one each time you want to invoke a method. Just remember that most operations need an instance created with the same prefix.

9.23.3 Member Function Documentation

9.23.3.1 deletefile()

```
void OpenZGY::Impl::ZgyUtils::deletefile (
    const std::string & filename,
    bool missing_ok ) [virtual]
```

Delete a file. Works both for local and cloud files.

Note that the instance must be of the correct (local or cloud) type.

Implements [OpenZGY::IZgyUtils](#).


The documentation for this class was generated from the following file:

- [api.cpp](#)

9.24 OpenZGY::Impl::ZgyWriter Class Reference

Concrete implementation of [IZgyWriter](#).

Inheritance diagram for OpenZGY::Impl::ZgyWriter:



Public Member Functions

- [ZgyWriter](#) (const [ZgyWriterArgs](#) &args)
Create a ZGY file and open it for writing.
- virtual [~ZgyWriter](#) ()
Automatically close the file when it goes out of scope.
- void [write](#) (const size3i_t &start, const size3i_t &size, const float *data) const override
Write an arbitrary region.
- void [write](#) (const size3i_t &start, const size3i_t &size, const std::int16_t *data) const override
Write an arbitrary region with no conversion.
- void [write](#) (const size3i_t &start, const size3i_t &size, const std::int8_t *data) const override
Write an arbitrary region with no conversion.
- void [writeconst](#) (const size3i_t &start, const size3i_t &size, const float *data) const override
Write all-constant data.
- void [writeconst](#) (const size3i_t &start, const size3i_t &size, const std::int16_t *data) const override
Write an arbitrary region with no conversion.
- void [writeconst](#) (const size3i_t &start, const size3i_t &size, const std::int8_t *data) const override
Write an arbitrary region with no conversion.
- void [finalize](#) (const std::vector< [DecimationType](#) > &decimation, const std::function< bool(std::int64_t, std::int64_t)> &progress, bool force=false)
Generate low resolution data, statistics, and histogram.
- void [close](#) ()
Flush the file to disk and close it.
- bool [errorflag](#) () const override
- void [set_errorflag](#) (bool value) override

Additional Inherited Members

9.24.1 Detailed Description

Concrete implementation of [IZgyWriter](#).

9.24.2 Constructor & Destructor Documentation

9.24.2.1 ZgyWriter()

```
OpenZGY::Impl::ZgyWriter::ZgyWriter (
    const ZgyWriterArgs & args )
```

Create a ZGY file and open it for writing.

9.24.2.2 ~ZgyWriter()

```
virtual OpenZGY::Impl::ZgyWriter::~ZgyWriter ( ) [virtual]
```

Automatically close the file when it goes out of scope.

Application code is encouraged to close the file explicitly. The destructor is just there as a fallback. [Errors](#) caught in the fallback will be logged to stderr and otherwise ignored.

9.24.3 Member Function Documentation

9.24.3.1 close()

```
void OpenZGY::Impl::ZgyWriter::close ( ) [virtual]
```

Flush the file to disk and close it.

If the file has been written to, the application is encouraged to call [finalize\(\)](#) before [close\(\)](#). This gives more control over the process and allows using a progress callback to track generation of low resolution data.

The function won't bother with statistics, histogram, lowres if there has been an unrecoverable error. The headers might still be written out in case somebody wants to try some forensics.

The [ZgyWriter](#) destructor will call [close\(\)](#) if not done already, but that will catch and swallow any exception. Relying on the destructor to close the file is strongly discouraged.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.2 errorflag()

```
bool OpenZGY::Impl::ZgyWriter::errorflag ( ) const [override]
```

Return true if this open file has encountered an unrecoverable error. The error should previously have caused an exception to be thrown. If this flag is set, no further writes will be allowed.

Application code might check this flag if they are considering trying to recover from an error. Internally the flag is also checked and if set it will (mostly) prevent other writes from being done.

Implementation note: Currently the [ZgyInternalMeta](#) and [ZgyInternalBulk](#) instances each contains an `_is_bad` member. The reader or writer is considered bad if either of those are set. This scheme improves isolation somewhat, but TODO-Low it might backfire. If writing metadata to file failed, the bulk accessor should probably behave as if it also has seen an error.

Currently only the [ZgyWriter](#) uses this mechanism. It might not make that much sense in [ZgyReader](#), because as long as opening the file succeeded no operation should manage to corrupt it.

9.24.3.3 finalize()

```
void OpenZGY::Impl::ZgyWriter::finalize (
    const std::vector< DecimationType > & decimation,
    const std::function< bool(std::int64_t, std::int64_t)> & progress,
    bool force = false ) [virtual]
```

Generate low resolution data, statistics, and histogram.

This method will be called automatically from [close\(\)](#), but in that case it is not possible to request a progress callback.

If the processing raises an exception the data is still marked as clean. Called can force a retry by passing `force=True`.

The C++ code is very different from Python because it needs an entirely different approach to be performant.

Parameters

<i>decimation</i>	Optionally override the decimation algorithms by passing an array of DecimationType with one entry for each level of detail. If the array is too short then the last entry is used for subsequent levels.
<i>progress</i>	Function(done, total) called to report progress. If it returns False the computation is aborted. Will be called at least one, even if there is no work.
<i>force</i>	If true, generate the low resolution data even if it appears to not be needed. Use with caution. Especially if writing to the cloud, where data should only be written once.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.4 set_errorflag()

```
void OpenZGY::Impl::ZgyWriter::set_errorflag (
    bool value ) [override]
```

Force the error flag for this open file to true or false. This should normally be done only for testing.

9.24.3.5 write() [1/3]

```
void OpenZGY::Impl::ZgyWriter::write (
    const size3i_t & start,
    const size3i_t & size,
    const float * data ) const [override], [virtual]
```

Write an arbitrary region.

This will apply conversion float -> storage if needed.

A read/modify/write will be done if the region's start and size doesn't align with bricksizes. When writing to the cloud this read/modify/write may incur performance and size penalties. So do write brick aligned data if possible. The same applies to writing compressed data where r/m/w can cause a severe loss of quality.

The start position refers to the specified lod level. At lod 0 start + data.size can be up to the survey size. At lod 1 the maximum is just half that, rounded up.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.6 write() [2/3]

```
void OpenZGY::Impl::ZgyWriter::write (
    const size3i_t & start,
    const size3i_t & size,
    const std::int16_t * data ) const [override], [virtual]
```

Write an arbitrary region with no conversion.

As the write overload with a float buffer but only works for files with SampleDataType::int16 and does not scale the samples.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.7 write() [3/3]

```
void OpenZGY::Impl::ZgyWriter::write (
    const size3i_t & start,
    const size3i_t & size,
    const std::int8_t * data ) const [override], [virtual]
```

Write an arbitrary region with no conversion.

As the write overload with a float buffer but only works for files with `SampleDataType::int8` and does not scale the samples.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.8 writeconst() [1/3]

```
void OpenZGY::Impl::ZgyWriter::writeconst (
    const size3i_t & start,
    const size3i_t & size,
    const float * data ) const [override], [virtual]
```

Write all-constant data.

Works as the corresponding write but the entire region is set to the same value. So the provided data buffer needs just one value, or alternatively can be passed as `&scalar_value`.

Calling this method is faster than filling a buffer with constant values and calling write. But it produces the exact same result. This is because write will automatically detect whether the input buffer is all constant.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.9 writeconst() [2/3]

```
void OpenZGY::Impl::ZgyWriter::writeconst (
    const size3i_t & start,
    const size3i_t & size,
    const std::int16_t * data ) const [override], [virtual]
```

Write an arbitrary region with no conversion.

As the writeconst overload with a float buffer but only works for files with `SampleDataType::int16` and does not scale the samples.

Implements [OpenZGY::IZgyWriter](#).

9.24.3.10 writeconst() [3/3]

```
void OpenZGY::Impl::ZgyWriter::writeconst (
    const size3i_t & start,
    const size3i_t & size,
    const std::int8_t * data ) const [override], [virtual]
```

Write an arbitrary region with no conversion.

As the write overload with a float buffer but only works for files with SampleDataType::int8 and does not scale the samples.

Implements [OpenZGY::IZgyWriter](#).

The documentation for this class was generated from the following file:

- [api.cpp](#)

9.25 OpenZGY::ZgyWriterArgs Class Reference

Argument package for creating a ZGY file.

```
#include <api.h>
```

Public Types

- typedef double **float64_t**
- typedef std::array< std::array< float64_t, 2 >, 4 > **corners_t**
- typedef std::pair< std::shared_ptr< const void >, std::int64_t > **rawdata_t**
- typedef std::function< rawdata_t(const rawdata_t &, const std::array< int64_t, 3 > &)> **compressor_t**

Public Member Functions

- void **dump** (std::ostream &out)

Output in human readable form for debugging.
- **ZgyWriterArgs** & **filename** (const std::string &value)

Set file to open.
- **ZgyWriterArgs** & **iocontext** (const **IOContext** *value)

Set credentials and other configuration.
- **ZgyWriterArgs** & **compressor** (const compressor_t &value)

Set functor for compressing full resolution data.
- **ZgyWriterArgs** & **compressor** (const std::string &name, const std::vector< std::string > &args)

Set functor for compressing full resolution data.
- **ZgyWriterArgs** & **zfp_compressor** (const std::string &name, float snr)

Set functor for compressing full resolution data.
- **ZgyWriterArgs** & **lodcompressor** (const compressor_t &value)

Set functor for compressing low resolution data.
- **ZgyWriterArgs** & **lodcompressor** (const std::string &name, const std::vector< std::string > &args)

Set functor for compressing low resolution data.

- [ZgyWriterArgs & zfp_lodcompressor](#) (const std::string &name, float snr)
Set functor for compressing low resolution data.
- [ZgyWriterArgs & size](#) (std::int64_t ni, std::int64_t nj, std::int64_t nk)
Set size of the survey.
- [ZgyWriterArgs & bricksize](#) (std::int64_t ni, std::int64_t nj, std::int64_t nk)
Set size of one brick.
- [ZgyWriterArgs & datatype](#) (SampleDataType value)
Set type of samples in each brick.
- [ZgyWriterArgs & datarange](#) (float lo, float hi)
Set scaling factors.
- [ZgyWriterArgs & zunit](#) (UnitDimension dimension, const std::string &name, double factor)
Set vertical unit.
- [ZgyWriterArgs & hunit](#) (UnitDimension dimension, const std::string &name, double factor)
Set horizontal unit.
- [ZgyWriterArgs & ilstart](#) (float value)
Set first (ordinal 0) inline number.
- [ZgyWriterArgs & ilinc](#) (float value)
Set inline number increment between two adjacent ordinal values.
- [ZgyWriterArgs & xlstart](#) (float value)
Set first (ordinal 0) crossline number.
- [ZgyWriterArgs & xlinc](#) (float value)
Set crossline number increment between two adjacent ordinal values.
- [ZgyWriterArgs & zstart](#) (float value)
Set first time/depth.
- [ZgyWriterArgs & zinc](#) (float value)
Set increment (distance between samples) in vertical direction.
- [ZgyWriterArgs & corners](#) (const corners_t &value)
Set survey corner points in world coordinates.
- [ZgyWriterArgs & metafrom](#) (const std::shared_ptr< [OpenZGY::IZgyReader](#) > &)
Copy metadata from existing file.

9.25.1 Detailed Description

Argument package for creating a ZGY file.

This is a short lived helper class for passing arguments to the functions that create a ZGY file. Needed because there are a lot of arguments and C++ doesn't allow keyword arguments. Do NOT use this class for holding on to the information.

Information not set explicitly will be defaulted. The following two statements give the same result:

```
ZgyWriterArgs default_args = ZgyWriterArgs();

ZgyWriterArgs default_args = ZgyWriterArgs()
    .filename("")
    .iocontext(nullptr)
    .compressor(nullptr)
    .lodcompressor(nullptr)
    .size(0, 0, 0)
    .bricksizes(64, 64, 64)
    .datatype(SampleDataType::float32)
    .datarange(0, -1)
    .zunit(UnitDimension::unknown, "", 1.0)
    .hunit(UnitDimension::unknown, "", 1.0)
    .ilstart(0)
    .ilinc(0)
    .xlstart(0)
    .xlinc(0)
    .zstart(0)
    .zinc(0)
    .corners(ZgyWriterArgs::corners_t{0,0,0,0,0,0,0,0});
```

9.25.2 Member Function Documentation

9.25.2.1 bricksize()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::bricksize (
    std::int64_t ni,
    std::int64_t nj,
    std::int64_t nk )
```

Set size of one brick.

Almost always (64,64,64). Change at your own peril.

9.25.2.2 compressor()

```
ZgyWriterArgs & OpenZGY::ZgyWriterArgs::compressor (
    const std::string & name,
    const std::vector< std::string > & args )
```

Set functor for compressing full resolution data.

This overload uses a factory to look up the compressor.

9.25.2.3 corners()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::corners (
    const corners_t & value )
```

Set survey corner points in world coordinates.

The corners are ordered origin, last inline (i.e. i=last, j=0), last crossline, diagonal.

9.25.2.4 datarange()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::datarange (
    float lo,
    float hi )
```

Set scaling factors.

For integral storage this specifies the two floating point numbers that correspond to the lowest and highest representable integer value. So for int8 files, -128 will be converted to "lo" and +127 will be converted to "hi".

9.25.2.5 hunit()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::hunit (
    UnitDimension dimension,
    const std::string & name,
    double factor )
```

Set horizontal unit.

Parameters

<i>dimension</i>	cartesian length or (unsupported) polat coordinates,
<i>name</i>	for annotation only.
<i>factor</i>	multiply by this factor to convert from storage units to SI units.

9.25.2.6 ilinc()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::ilinc (
    float value )
```

Set inline number increment between two adjacent ordinal values.

For maximum portability the inline and crossline start and increment should be integral numbers. Some applications might choose to convert them to int.

9.25.2.7 ilstart()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::ilstart (
    float value )
```

Set first (ordinal 0) inline number.

For maximum portability the inline and crossline start and increment should be integral numbers. Some applications might choose to convert them to int.

9.25.2.8 iocontext()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::iocontext (
    const IOContext * value )
```

Set credentials and other configuration.

This depends on the back-end. For local files you normally don't need to pass anything here.

9.25.2.9 lodcompressor()

```
ZgyWriterArgs & OpenZGY::ZgyWriterArgs::lodcompressor (
    const std::string & name,
    const std::vector< std::string > & args )
```

Set functor for compressing low resolution data.

This overload uses a factory to look up the compressor.

9.25.2.10 metafrom()

```
ZgyWriterArgs & OpenZGY::ZgyWriterArgs::metafrom (
    const std::shared_ptr< OpenZGY::IZgyReader > & reader )
```

Copy metadata from existing file.

Set most of the metadata from an open file descriptor. Typically used when the file to be created is to be computed from an existing file. Typically this will be called first so the settings don't inadvertently shadow something set explicitly.

9.25.2.11 size()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::size (
    std::int64_t ni,
    std::int64_t nj,
    std::int64_t nk )
```

Set size of the survey.

Parameters

<i>ni</i>	number of inlines (slowest varying index).
<i>nj</i>	number of crosslines.
<i>nk</i>	number of samples per trace (fastest).

9.25.2.12 xlinc()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::xlinc (
    float value )
```

Set crossline number increment between two adjacent ordinal values.

For maximum portability the inline and crossline start and increment should be integral numbers. Some applications might choose to convert them to int.

9.25.2.13 xlstart()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::xlstart (
    float value )
```

Set first (ordinal 0) crossline number.

For maximum portability the inline and crossline start and increment should be integral numbers. Some applications might choose to convert them to int.

9.25.2.14 zfp_compressor()

```
ZgyWriterArgs & OpenZGY::ZgyWriterArgs::zfp_compressor (
    const std::string & name,
    float snr )
```

Set functor for compressing full resolution data.

This overload uses a factory to look up the ZGY compressor. It is just a convenience that is shorter to type.

9.25.2.15 zfp_lodcompressor()

```
ZgyWriterArgs & OpenZGY::ZgyWriterArgs::zfp_lodcompressor (
    const std::string & name,
    float snr )
```

Set functor for compressing low resolution data.

This overload uses a factory to look up the ZGY compressor. It is just a convenience that is shorter to type.

9.25.2.16 zinc()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::zinc (
    float value )
```

Set increment (distance between samples) in vertical direction.

Vertical annotation is generally safe to have non-integral.

9.25.2.17 zstart()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::zstart (
    float value )
```

Set first time/depth.

Vertical annotation is generally safe to have non-integral.

9.25.2.18 zunit()

```
ZgyWriterArgs& OpenZGY::ZgyWriterArgs::zunit (
    UnitDimension dimension,
    const std::string & name,
    double factor )
```

Set vertical unit.

Parameters

<i>dimension</i>	time or depth (a.k.a. length).
<i>name</i>	for annotation only.
<i>factor</i>	Multiply by this factor to convert from storage units to SI units.

The documentation for this class was generated from the following files:

- [api.h](#)
- [api.cpp](#)

Chapter 10

File Documentation

10.1 api.cpp File Reference

Implements the pure interfaces of the API.

```
#include "api.h"  
#include "exception.h"  
#include "impl/enum.h"  
#include "impl/file.h"  
#include "impl/file_sd.h"  
#include "impl/meta.h"  
#include "impl/bulk.h"  
#include "impl/databuffer.h"  
#include "impl/ttransform.h"  
#include "impl/lodalgo.h"  
#include "impl/statisticdata.h"  
#include "impl/histogramdata.h"  
#include "impl/genlod.h"  
#include "impl/compression.h"
```

Classes

- class [OpenZGY::Impl::ZgyMeta](#)
High level API for reading and writing ZGY files.
- class [OpenZGY::Impl::ZgyMetaAndTools](#)
Add coordinate conversion to the concrete [ZgyMeta](#) class.
- class [OpenZGY::Impl::ZgyReader](#)
Concrete implementation of [IZgyReader](#).
- class [OpenZGY::Impl::ZgyWriter](#)
Concrete implementation of [IZgyWriter](#).
- class [OpenZGY::Impl::ZgyUtils](#)
Concrete implementation of [IZgyUtils](#).

Namespaces

- [OpenZGY](#)
The entire public API is in this namespace.
- [OpenZGY::Impl](#)
Implementation of the abstract interfaces in [OpenZGY](#).
- [OpenZGY::Formatters](#)
operator<< for readable output of enums etc.

Functions

- `std::string OpenZGY::Formatters::enumToString (SampleDataType value)`
Return the string representation of the input enum type.
- `std::string OpenZGY::Formatters::enumToString (UnitDimension value)`
Return the string representation of the input enum type.
- `std::string OpenZGY::Formatters::enumToString (DecimationType value)`
Return the string representation of the input enum type.
- `std::ostream & OpenZGY::Formatters::operator<< (std::ostream &os, SampleDataType value)`
Output the string representation of the input enum type.
- `std::ostream & OpenZGY::Formatters::operator<< (std::ostream &os, UnitDimension value)`
Output the string representation of the input enum type.
- `std::ostream & OpenZGY::Formatters::operator<< (std::ostream &os, DecimationType value)`
Output the string representation of the input enum type.

10.1.1 Detailed Description

Implements the pure interfaces of the API.

10.2 api.h File Reference

IZgyReader, IZgyWriter, and other user visible classes.

```
#include <cstdint>
#include <vector>
#include <array>
#include <ostream>
#include <iostream>
#include <functional>
#include <memory>
```


Classes

- class [OpenZGY::SampleStatistics](#)
Statistics of all sample values on the file.
- class [OpenZGY::SampleHistogram](#)
Histogram of all sample values on the file.
- class [OpenZGY::ZgyWriterArgs](#)
Argument package for creating a ZGY file.
- class [OpenZGY::IZgyMeta](#)
Base class of [IZgyReader](#) and [IZgyWriter](#).
- class [OpenZGY::IZgyTools](#)
Base class of [IZgyReader](#) and [IZgyWriter](#).
- class [OpenZGY::IZgyReader](#)
Main API for reading ZGY files.
- class [OpenZGY::IZgyWriter](#)
Main API for creating ZGY files.
- class [OpenZGY::IZgyUtils](#)
Operations other than read and write.
- class [OpenZGY::ProgressWithDots](#)
Simple progress bar.

Namespaces

- [OpenZGY](#)
The entire public API is in this namespace.
- [OpenZGY::Errors](#)
Exceptions that can be thrown by [OpenZGY](#).
- [OpenZGY::Impl](#)
Implementation of the abstract interfaces in [OpenZGY](#).
- [OpenZGY::Formatters](#)
operator<< for readable output of enums etc.

Enumerations

- enum [OpenZGY::SampleDataType](#) { **unknown** = 1000, **int8** = 1001, **int16** = 1002, **float32** = 1003 }
- enum [OpenZGY::UnitDimension](#) { **unknown** = 2000, **time** = 2001, **length** = 2002, **arcangle** = 2003 }
- enum [OpenZGY::DecimationType](#) {
[OpenZGY::DecimationType::LowPass](#) = 100, [OpenZGY::DecimationType::WeightedAverage](#), [OpenZGY::DecimationType::Average](#), [OpenZGY::DecimationType::Median](#),
[OpenZGY::DecimationType::Minimum](#), [OpenZGY::DecimationType::Maximum](#), [OpenZGY::DecimationType::MinMax](#), [OpenZGY::DecimationType::Decimate](#),
[OpenZGY::DecimationType::DecimateSkipNaN](#), [OpenZGY::DecimationType::DecimateRandom](#), [OpenZGY::DecimationType::AllZero](#), [OpenZGY::DecimationType::WhiteNoise](#),
[OpenZGY::DecimationType::MostFrequent](#), [OpenZGY::DecimationType::MostFrequentNon0](#), [OpenZGY::DecimationType::AverageNon0](#) }

Functions

- `std::ostream & OpenZGY::Formatters::operator<< (std::ostream &os, SampleDataType value)`
Output the string representation of the input enum type.
- `std::ostream & OpenZGY::Formatters::operator<< (std::ostream &os, UnitDimension value)`
Output the string representation of the input enum type.
- `std::ostream & OpenZGY::Formatters::operator<< (std::ostream &os, DecimationType value)`
Output the string representation of the input enum type.

10.2.1 Detailed Description

IZgyReader, IZgyWriter, and other user visible classes.

This file contains the public [OpenZGY](#) API.

The API is modeled roughly after the API exposed by the Python wrapper around the existing C++ ZGY-Public API. This is probably just as good a starting point than anything else. And it makes testing simpler for those tests that compare the old and new behavior.

[OpenZGY::IZgyMeta](#)

- Has a private reference to a `impl.meta.ZgyInternalMeta` instance.
- Contains a large number of properties exposing meta data, most of which will present information from the `ZgyInternalMeta` in a way that is simpler to use and doesn't depend on the file version.
- End users will access methods from this class. Most likely via the derived `ZgyReader` and `ZgyWriter` classes. The end users might not care that there is a separate base class.

`OpenZGY::ZgyMetaAndTools` extends `IZgyMeta`

- Add coordinate conversion routines to a `ZgyMeta` instance.

`OpenZGY::ZgyReader` extends `ZgyMetaAndTools` with `read`, `readconst`, `close` `OpenZGY::ZgyWriter` extends `ZgyMetaAndTools` with `write`, `writeconst`, `finalize`, `close`

- Has a private reference to a `impl.meta.ZgyInternalBulk` instance.
- Add bulk read and write functionality, forwarding the requests to the internal bulk instance.
- These classes with their own and inherited methods and properties comprise the public [OpenZGY](#) API.
- Currently the `ZgyWriter` does not expose the `bulk read()` function but it does allow accessing all the metadata. Allowing `read()` might be added later if it appears to be useful. In practice this just means to let `ZgyWriter` inherit `ZgyReader`.

Note that enums and exceptions are problematic when it comes to encapsulation. Enums might be:

- Only visible in the public api. Often end up being mapped to a corresponding internal enum. No problem, but the mapping can be a bit tedious to maintain.
- Only visible internally. Possibly representing integer values written to file. Which makes them an implementation detail, which must absolutely not be exposed publically.
- Defined by the public api but passed unchanged from the api layer to the implementation layer. So there will be an include in some `impl/xxx.h` file to a part of the public API. This is frowned upon.
- Defined by the internal api but may need to be used from applications, i.e. also visible in the public api. There will be an include of e.g. `"impl/ugly.h"` from one of the public header files and/or application code. This is strongly discouraged except for testing.

Exceptions have similar issues. It is possible to catch all exceptions raised in the impl layer and convert those to exceptions owned by the api layer. But re-throwing an exception makes debugging harder.

10.3 example.h File Reference

Example program using the C++ API.

```
#include <openzgy/api.h>
#include <iostream>
#include <stdexcept>
#include <stdlib.h>
```

Functions

- void **copy** (const std::string &srcname, const std::string &dstname)
- int **main** (int argc, const char **argv)

10.3.1 Detailed Description

Example program using the C++ API.

To build this e.g. on Ubuntu Xenial: Compile:

```
g++ -std=c++11 -Iinclude -oexample -x c++ example.h -Lxenial-gcc54 -Wl,-rpath-link=xenial-gcc54 -lopenzgy
```

Run:

```
env LD_LIBRARY_PATH=xenial-gcc54 ./example fromfile.zgy tofile.zgy
```

10.4 exception.h File Reference

Defines exceptions that may be raised by OpenZGY.

```
#include <stdexcept>
```

Classes

- class [OpenZGY::Errors::ZgyError](#)
Exception base class for all exceptions thrown by OpenZGY.
- class [OpenZGY::Errors::ZgyFormatError](#)
Exception for corrupted or unsupported ZGY file.
- class [OpenZGY::Errors::ZgyCorruptedFile](#)
Exception when the ZGY file became corrupted while writing to it.
- class [OpenZGY::Errors::ZgyUserError](#)
Exception that might be caused by the calling application.
- class [OpenZGY::Errors::ZgyInternalError](#)
Exception that might be caused by a bug in OpenZGY.
- class [OpenZGY::Errors::ZgyEndOfFile](#)
Exception trying to read past EOF.
- class [OpenZGY::Errors::ZgySegmentsIsClosed](#)
Exception used internally to request a retry.
- class [OpenZGY::Errors::ZgyAborted](#)
Exception used to abort the computation.
- class [OpenZGY::Errors::ZgyMissingFeature](#)
Exception for missing feature.
- class [OpenZGY::Errors::ZgyIoError](#)
Exception from the I/O layer.

Namespaces

- [OpenZGY](#)
The entire public API is in this namespace.
- [OpenZGY::Errors](#)
Exceptions that can be thrown by [OpenZGY](#).

10.4.1 Detailed Description

Defines exceptions that may be raised by OpenZGY.

These classes are both visible to the [OpenZGY](#) public API and referenced directly from the implementation classes. I apologize for the broken encapsulation. Re-mapping the exceptions in the API layer didn't seem worth the trouble.

10.5 iocontext.h File Reference

Backend specific context.

```
#include "exception.h"  
#include <cstdint>  
#include <string>  
#include <vector>  
#include <functional>
```

Classes

- class [OpenZGY::IOContext](#)
Base class for backend specific context.

Namespaces

- [OpenZGY](#)
The entire public API is in this namespace.

10.5.1 Detailed Description

Backend specific context.

Class IOContext and derivatives are used to hold backend specific information such as authorization tokens.

Index

- ~ZgyWriter
 - OpenZGY::Impl::ZgyWriter, 52
- api.cpp, 63
- api.h, 64
- bricksiz
 - OpenZGY::ZgyWriterArgs, 58
- close
 - OpenZGY::IZgyReader, 22
 - OpenZGY::IZgyWriter, 29
 - OpenZGY::Impl::ZgyReader, 47
 - OpenZGY::Impl::ZgyWriter, 53
- compressor
 - OpenZGY::ZgyWriterArgs, 58
- corners
 - OpenZGY::ZgyWriterArgs, 58
- datarange
 - OpenZGY::ZgyWriterArgs, 58
- DecimationType
 - OpenZGY, 16
- deletefile
 - OpenZGY::IZgyUtils, 27
 - OpenZGY::Impl::ZgyUtils, 51
- errorflag
 - OpenZGY::Impl::ZgyWriter, 53
- example.h, 67
- exception.h, 67
- finalize
 - OpenZGY::IZgyWriter, 29
 - OpenZGY::Impl::ZgyWriter, 53
- hunit
 - OpenZGY::ZgyWriterArgs, 58
- ilinc
 - OpenZGY::ZgyWriterArgs, 59
- ilstart
 - OpenZGY::ZgyWriterArgs, 59
- iocontext
 - OpenZGY::ZgyWriterArgs, 59
- iocontext.h, 68
- List of exceptions, 13
- lodcompressor
 - OpenZGY::ZgyWriterArgs, 59
- metafrom
 - OpenZGY::ZgyWriterArgs, 59
- OpenZGY::Errors, 17
 - OpenZGY::Errors::ZgyAborted, 35
 - OpenZGY::Errors::ZgyCorruptedFile, 36
 - OpenZGY::Errors::ZgyEndOfFile, 37
 - OpenZGY::Errors::ZgyError, 37
 - OpenZGY::Errors::ZgyFormatError, 38
 - OpenZGY::Errors::ZgyInternalError, 39
 - OpenZGY::Errors::ZgyIoError, 40
 - OpenZGY::Errors::ZgyMissingFeature, 45
 - OpenZGY::Errors::ZgySegmentIsClosed, 48
 - OpenZGY::Errors::ZgyUserError, 49
- OpenZGY::Formatters, 18
- OpenZGY::IOContext, 19
 - toString, 19
- OpenZGY::IZgyMeta, 20
- OpenZGY::IZgyReader, 21
 - close, 22
 - read, 22, 23
 - readconst, 23
- OpenZGY::IZgyTools, 24
 - transform, 25
 - transform1, 26
- OpenZGY::IZgyUtils, 26
 - deletefile, 27
 - utils, 27
- OpenZGY::IZgyWriter, 28
 - close, 29
 - finalize, 29
 - write, 30
 - writeconst, 31
- OpenZGY::Impl, 18
- OpenZGY::Impl::ZgyMeta, 41
- OpenZGY::Impl::ZgyMetaAndTools, 43
 - transform, 44
 - transform1, 44
- OpenZGY::Impl::ZgyReader, 46
 - close, 47
 - read, 47
 - readconst, 48
 - ZgyReader, 46
- OpenZGY::Impl::ZgyUtils, 50
 - deletefile, 51
 - ZgyUtils, 50
- OpenZGY::Impl::ZgyWriter, 51
 - ~ZgyWriter, 52
 - close, 53
 - errorflag, 53
 - finalize, 53

- set_errorflag, [54](#)
 - write, [54](#)
 - writeconst, [55](#)
 - ZgyWriter, [52](#)
- OpenZGY::ProgressWithDots, [32](#)
 - operator(), [33](#)
 - ProgressWithDots, [32](#)
- OpenZGY::SampleHistogram, [33](#)
- OpenZGY::SampleStatistics, [34](#)
- OpenZGY::ZgyWriterArgs, [56](#)
 - bricksize, [58](#)
 - compressor, [58](#)
 - corners, [58](#)
 - datarange, [58](#)
 - hunit, [58](#)
 - ilinc, [59](#)
 - ilstart, [59](#)
 - iocontext, [59](#)
 - lodcompressor, [59](#)
 - metafrom, [59](#)
 - size, [60](#)
 - xlinc, [60](#)
 - xlstart, [60](#)
 - zfp_compressor, [60](#)
 - zfp_lodcompressor, [61](#)
 - zinc, [61](#)
 - zstart, [61](#)
 - zunit, [61](#)
- OpenZGY, [15](#)
 - DecimationType, [16](#)
 - SampleDataType, [17](#)
 - UnitDimension, [17](#)
- operator()
 - OpenZGY::ProgressWithDots, [33](#)
- ProgressWithDots
 - OpenZGY::ProgressWithDots, [32](#)
- read
 - OpenZGY::IZgyReader, [22](#), [23](#)
 - OpenZGY::Impl::ZgyReader, [47](#)
- readconst
 - OpenZGY::IZgyReader, [23](#)
 - OpenZGY::Impl::ZgyReader, [48](#)
- SampleDataType
 - OpenZGY, [17](#)
- set_errorflag
 - OpenZGY::Impl::ZgyWriter, [54](#)
- size
 - OpenZGY::ZgyWriterArgs, [60](#)
- toString
 - OpenZGY::IOContext, [19](#)
- transform
 - OpenZGY::IZgyTools, [25](#)
 - OpenZGY::Impl::ZgyMetaAndTools, [44](#)
- transform1
 - OpenZGY::IZgyTools, [26](#)
- OpenZGY::Impl::ZgyMetaAndTools, [44](#)
- UnitDimension
 - OpenZGY, [17](#)
- utils
 - OpenZGY::IZgyUtils, [27](#)
- write
 - OpenZGY::IZgyWriter, [30](#)
 - OpenZGY::Impl::ZgyWriter, [54](#)
- writeconst
 - OpenZGY::IZgyWriter, [31](#)
 - OpenZGY::Impl::ZgyWriter, [55](#)
- xlinc
 - OpenZGY::ZgyWriterArgs, [60](#)
- xlstart
 - OpenZGY::ZgyWriterArgs, [60](#)
- zfp_compressor
 - OpenZGY::ZgyWriterArgs, [60](#)
- zfp_lodcompressor
 - OpenZGY::ZgyWriterArgs, [61](#)
- ZgyReader
 - OpenZGY::Impl::ZgyReader, [46](#)
- ZgyUtils
 - OpenZGY::Impl::ZgyUtils, [50](#)
- ZgyWriter
 - OpenZGY::Impl::ZgyWriter, [52](#)
- zinc
 - OpenZGY::ZgyWriterArgs, [61](#)
- zstart
 - OpenZGY::ZgyWriterArgs, [61](#)
- zunit
 - OpenZGY::ZgyWriterArgs, [61](#)